

Query Binding and Value Binding

Block Group:	no group
Icon:	no icon

A Query Binding or Value Binding block contains all of the information that is configured in the Binding Dialog Box. See [Binding Dialog](#). These blocks are located in the dataflow model of the dataflow block that owns the target property.

For information on using dataflow blocks, see [Dataflow](#).

How to Add and Edit a Query Binding Block to a Dataflow Model

This block cannot be added via the Blocks pane. To add and edit a Query Binding block:

1. Drag the source node or metric to the target block property.
2. Drop the binding source on the target property in the Block Properties pane.

This opens the Binding dialog box.



Note

You cannot create a binding by dropping a node or metric on the target property in the Dataflow pane.

3. To configure Query Binding block properties, do one of the following:
 - Use the Binding dialog box. Changes affect the Query Binding block.
 - Open the dataflow model of the block that owns the target property of the binding.

How to Add a Value Binding Block to a Dataflow Model

This block cannot be added via the Blocks pane. To add and edit a Value Binding block:

1. Begin dragging the source block property to the target block property.
2. While dragging, press and hold the Ctrl key.
3. Drop the binding source on the binding target.

This opens the Binding dialog box and creates a Value Binding block for the target property.

4. To configure Value Binding block properties, do one of the following:
 - Use the Binding dialog box. Changes affect the Value Binding block.
 - Open the dataflow model of the block that owns the target property of the binding.

Input/Output Properties

The following properties of the Query Binding or Value Binding block can take input and give output.

- path (*string*)
- enabled (*boolean*)
- expression (*string*)
- mode (*enum*)
- offset (*enum*)
- Offset Value (*number*)
- input min (*number*)
- input max (*number*)
- output min (*number*)
- output max (*number*)
- gradient
- mapping
- case *n*
- then *n*
- default

path specifies the path to the binding source.

enabled specifies whether this block is enabled.

- **TRUE**—When the source property value changes, the target property updates.
- **FALSE**—The target property does not update when the source property changes.

expression specifies the string to use to format the source value. This creates the target value as a formatted string. The **expression** can include a number format pattern. See [Scripting and Syntax](#). The **expression** can also include other strings, such as units. Number format patterns must be in square brackets ([]). The string value enclosed in square brackets becomes the exact source value, as a string.

mode specifies the type of calculation to perform on the source value. If the mapping property is set to a value other than none, the mapping overrides the mode. The value of the mode property can be one of the following:

- **value**—Returns the exact source value.
- **formatted**—Returns the source value, reformatted as specified by a default formatting string.
- **expression**—Returns the source value, reformatted as specified by a custom formatting string. Requires the **expression** property to be set.
- **offset**—Returns the result of a calculation that uses the source value, an operator, and a number. Requires the **offset** and **Offset Value** properties to be set.
- **scale**—Finds the source value's position on an original scale, and returns the corresponding value on a new scale. Requires the **input min**, **input max**, **output min**, and **output max** values to be set.
- **gradient**—Finds the source value's position on an original scale, and returns the corresponding color on a gradient. Requires the **input min**, **input max**, and **gradient** values to be set.

offset specifies the offset operator that is used to modify the target value. The **offset** property applies only when the **mode** property is set to **offset**. The value of the **offset** property can be one of the following:

- **add**—The source value and **Offset Value** property are added together.
- **subtract**—The **Offset Value** property is subtracted from the source value.
- **multiply**—The source value and **Offset Value** property are multiplied together.
- **divide**—The source value is divided by the **Offset Value** property. A decimal value is returned.
- **modulo**—The source value is divided by the **Offset Value** property. The remainder is returned.
- **divide (int)**—The source value is divided by the **Offset Value** property. The quotient is returned, rounded down to the nearest integer.

Offset Value specifies the number that is used to modify the target value. The **Offset Value** property applies only when the **mode** property is set to **offset**.

input min specifies the lower bound of the original scale. The **input min** property applies only when the **mode** property is set to **scale** or **gradient**.

input max specifies the upper bound of the original scale. The **input max** property applies only when the **mode** property is set to **scale** or **gradient**.

output min specifies the lower bound of the new scale. The **output min** property applies only when the **mode** property is set to **scale**.

output max specifies the upper bound of the new scale. The **output max** property applies only when the **mode** property is set to **scale**.

gradient determines the colors for a gradient. For information about editing a gradient, see [Fill and Border Pop-Ups](#). The **gradient** property applies only when the **mode** property is set to **gradient**.

mapping determines the type of mapping. The value of the mapping property can be one of the following:

- **none**—No mapping is used. Instead, the type of calculation that is specified by the mode property is used.
- **number**—The input value is treated as a number.
- **string**—The input value is treated as a string.

- **enum**—The input value is treated as an enum value.
- **bool**—The input value is treated as a Boolean value.

case *n* specifies a test value to compare with the source value.

then *n* specifies a value to assign to the target if the expression with **case *n*** evaluates to TRUE. See [Binding Dialog](#).

default specifies a value to assign to the target if none of the **mapping** expressions evaluate to TRUE. See [Binding Dialog](#).

Output Property

The following property of the Query Binding or Value Binding block can give output but cannot take input.

- **output**

output returns the target value.

LOG10E

[Scripting and Syntax](#)

From:
<https://wiki.dglogik.com/> - **DGLogik**

Permanent link:
https://wiki.dglogik.com/dglux5_wiki:dataflow:dataflow_blocks_reference:bindings:home

Last update: **2021/09/20 15:02**

